

# **AGRIPHAGE-CMM CHEMIGATION**

**Instructions for the Application of AgriPhage-CMM by Chemigation to Tomatoes**

## **AGRIPHAGE-CMM**

**Bactericide for use on tomatoes**

[Biological control for bacterial canker on tomatoes]

**It is a violation of Federal law to use this product in a manner inconsistent with its labeling.**

**The labeling must be in possession of the user at the time of application.**

**Read the label affixed to the container for AgriPhage-CMM before applying.**

**Use of AgriPhage-CMM according to this labeling is subject to the use precautions and limitations imposed by the label affixed to the container for AgriPhage-CMM.**



OmniLytics, Inc.  
9075 South Sandy Parkway  
Sandy, Utah 84070  
801-746-3600  
[www.omnilytics.com](http://www.omnilytics.com)  
EPA Reg. No. 67986-6

## **Instructions Applicable to All Chemigation Types**

- 1) Apply this product only through drip (trickle) or sprinkler (including center pivot, lateral move, end tow, side (wheel) roll, traveler, big gun, solid set, or hand move) irrigation systems. Do not apply this product through any other type of irrigation system.
- 2) Crop injury, lack of effectiveness, or illegal pesticide residues in the crop can result from non-uniform distribution of treated water.
- 3) If you have questions about calibration, you should contact State Extension Service specialists, equipment manufacturers or other experts.
- 4) Do not connect an irrigation system (including greenhouse systems) used for pesticide application to a public water system unless the pesticide label-prescribed safety devices for public water systems are in place.
- 5) A person knowledgeable of the chemigation system and responsible for its operation, or under the supervision of the responsible person, shall shut the system down and make necessary adjustments should the need arise.

## **Instructions for Chemigation Systems Connected to Public Water Systems**

- 1) Public water system means a system for the provision to the public of piped water for human consumption if such system has at least 15 service connections or regularly serves an average of at least 25 individuals daily at least 60 days out of the year.
- 2) Chemigation systems connected to public water systems must contain a functional, reduced-pressure zone, backflow preventer (RPZ) or the functional equivalent in the water supply line upstream from the point of pesticide introduction. As an option to the RPZ, the water from the public water system should be discharged into a reservoir tank prior to pesticide introduction. There shall be a complete physical break (air gap) between the flow outlet end of the fill pipe and the top or overflow rim of the reservoir tank of at least twice the inside diameter of the fill pipe.
- 3) The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump.
- 4) The pesticide injection pipeline must contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.
- 5) The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops, or in cases where there is no water pump, when the water pressure decreases to the point where pesticide distribution is adversely affected.
- 6) Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.

- 7) Do not apply when wind speed favors drift beyond the area intended for treatment.
- 8) Agitate the supply tank immediately after adding AgriPhage-CMM.
- 9) AgriPhage-CMM is to be applied continuously for the duration of the water application.
- 10) Apply AgriPhage-CMM at a rate of 1 to 2 pints per acre. Repeat application 1-3 times per week.

### **Instructions for Sprinkler Chemigation**

- 1) The system must contain a functional check valve, vacuum relief valve, and low pressure drain appropriately located on the irrigation pipeline to prevent water source contamination from backflow.
- 2) The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump.
- 3) The pesticide injection pipeline must also contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.
- 4) The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops.
- 5) The irrigation line or water pump must include a functional pressure switch, which will stop the water pump motor when the water pressure decreases to the point where pesticide distribution is adversely affected.
- 6) Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.
- 7) Do not apply when wind speed favors drift beyond the area intended for treatment.
- 8) Agitate the supply tank immediately after adding AgriPhage-CMM.
- 9) AgriPhage-CMM is to be applied continuously for the duration of the water application.
- 10) Apply AgriPhage-CMM at a rate of 1 to 2 pints per acre. Repeat application 1-3 times per week.

### **Instructions for Drip (Trickle) Chemigation**

- 1) The system must contain a functional check valve, vacuum relief valve and low pressure drain appropriately located on the irrigation pipeline to prevent water source contamination from backflow.
- 2) The pesticide injection pipeline must contain a functional, automatic, quick-closing check valve to prevent the flow of fluid back toward the injection pump.
- 3) The pesticide injection pipeline must also contain a functional, normally closed, solenoid-operated valve located on the intake side of the injection pump and connected to the

system interlock to prevent fluid from being withdrawn from the supply tank when the irrigation system is either automatically or manually shut down.

- 4) The system must contain functional interlocking controls to automatically shut off the pesticide injection pump when the water pump motor stops.
- 5) The irrigation line or water pump must include a functional pressure switch, which will stop the water pump motor when the water pressure decreases to the point where pesticide distribution is adversely affected.
- 6) Systems must use a metering pump, such as a positive displacement injection pump (e.g., diaphragm pump) effectively designed and constructed of materials that are compatible with pesticides and capable of being fitted with a system interlock.
- 7) Agitate the supply tank immediately after adding AgriPhage-CMM.
- 8) AgriPhage-CMM is to be applied continuously for the duration of the water application.
- 9) Apply AgriPhage-CMM at a rate of 1 to 2 pints per acre. Repeat application 1-3 times per week.