



REFERENCE CARD

SYSTEM REQUIREMENTS

MINIMUM CONFIGURATION

- ☐ Windows® 95 or Windows 98 (Windows NT and Windows 2000 are not supported)
- ☐ 133 MHz or faster Intel® Pentium® or AMD® K6™ processor, or 200 MHz processor with supported 3D accelerator
- ☐ 32 MB RAM
- ☐ 8x or faster CD-ROM drive (1200K/second transfer rate) using 32-bit Windows 95/98 driver
- ☐ High Color (16-bit) capable 2 MB PCI or AGP video card with DirectX™ 7.0a compliant driver,
- ☐ 30 MB free hard disk space plus space for saved games (additional space required for Windows swap-file and DirectX 7.0 installation).
- ☐ DirectX 7.0a compatible sound card; Keyboard; Mouse

RECOMMENDED CONFIGURATION

- ☐ 300 MHz or faster Pentium II processor,
- ☐ 64 MB RAM
- ☐ 16x or faster CD-ROM drive (2400K/second transfer rate)
- ☐ 100 MB hard disk space plus space for saved games
- ☐ Supported 3-D graphics accelerator
- ☐ Supported gamepad

NOTE: Gameplay documentation is provided on-disc. (► Using the Electronic Documentation on p. 12.) If you would like to receive the printed manual, please see the order form on the back cover.

EA SPORTS

1 MADDEN NFL 2000

REQUIRED FOR MULTIPLAYER GAMES

NETWORK (2 PLAYERS; 2 PCs)

- ☐ IPX compliant network
- ☐ Network card

MODEM (2 PLAYERS; 2 PCs)

- ☐ 100% Hayes®-compatible 28.8 Kbps or faster modem
- ☐ High speed serial port (16550 UART)

SERIAL PLAY (2 PLAYERS; 2 PCs)

- ☐ Null modem cable
- ☐ High speed serial port (16550 UART)

TCP/IP PLAY (2 PLAYERS; 2 PCs)

- ☐ Internet connection via Internet Service Provider (ISP) with a 28.8 Kbps connection or better

SUPPORTED 3D GRAPHICS CHIPSETS & APIS

- ☐ 3Dfx Voodoo3™, 3Dfx Banshee™, 3Dfx Voodoo2, Nvidia™ TNT2™, Nvidia™ TNT™, or other recent Direct3D capable chipset; 3Dfx Voodoo2 SLI, 3D NOW!™, Dolby Surround Sound™, DirectSound™ 3D, Creative Labs Environmental Audio™

SUPPORTED INPUT DEVICES

- ☐ Keyboard, Mouse, Gravis® Gamepad Pro, Microsoft® SideWinder Gamepad™

DISK PREPARATION

Before you install any software, it is critical that your hard drive is in proper working order. We recommend running ScanDisk and Disk Defragmenter.

ScanDisk searches your hard drive for lost allocation units as well as cross-linked files and directories. Disk Defragmenter ensures that your data is sorted properly. Failure to verify this may result in corrupt data.

TO RUN SCANDISK:

1. Left-click the **Start** button from the Windows Taskbar. The Start menu opens.
2. From the Start menu, select **Run**.
3. In the Run dialog box, type **scandisk**, then click **OK**. The Setup screen appears.
 - ☐ Make sure a check mark appears in the Automatically Fix Errors box, then select the drive to which you are installing the game (e.g., C:).
4. Click **START** to begin ScanDisk.

TO RUN DISK DEFRAGMENTER:

1. Left-click the **Start** button from the Windows Taskbar. The Start menu opens.
2. From the Start menu, select **Run**.
3. In the Run dialog box, type **defrag**, then click **OK**. The Setup screen appears.
 - ☐ Select the drive to which you are installing the game.
4. Click **OK** to begin Disk Defragmenter.

DIRECTX 7.0a INSTALLATION NOTES

READ THIS SECTION COMPLETELY BEFORE PLAYING MADDEN NFL™ 2000 OR INSTALLING THE DIRECTX 7.0a DRIVERS.

DirectX 7.0a is an Application Programming Interface (API) that gives Windows 95/98 based applications high-performance, real-time access to your hardware, while reducing the complexity of installing and configuring your hardware. This makes the DirectX 7.0a API well suited for Windows 95/98 games.

Madden NFL 2000 uses the DirectX 6.0 API and includes DirectX 7.0a (the latest version of DirectX at the time of release) files which you can install.

Two DirectX 7.0a components, DirectDraw and DirectSound, may require updating your video card and sound card drivers respectively for proper operation of these components. Using video card and sound card drivers that do not support DirectX 7.0a will result in display and audio problems in DirectX 7.0a applications.

REQUIRED FOR MULTIPLAYER GAMES

NETWORK (2 PLAYERS; 2 PCs)

- ☐ IPX compliant network
- ☐ Network card

MODEM (2 PLAYERS; 2 PCs)

- ☐ 100% Hayes®-compatible 28.8 Kbps or faster modem
- ☐ High speed serial port (16550 UART)

SERIAL PLAY (2 PLAYERS; 2 PCs)

- ☐ Null modem cable
- ☐ High speed serial port (16550 UART)

TCP/IP PLAY (2 PLAYERS; 2 PCs)

- ☐ Internet connection via Internet Service Provider (ISP) with a 28.8 Kbps connection or better

SUPPORTED 3D GRAPHICS CHIPSETS & APIS

- ☐ 3Dfx Voodoo3™, 3Dfx Banshee™, 3Dfx Voodoo2, Nvidia™ TNT2™, Nvidia™ TNT™, or other recent Direct3D capable chipset; 3Dfx Voodoo2 SLI, 3D NOW!™, Dolby Surround Sound™, DirectSound™ 3D, Creative Labs Environmental Audio™

SUPPORTED INPUT DEVICES

- ☐ Keyboard, Mouse, Gravis® Gamepad Pro, Microsoft® SideWinder Gamepad™

During DirectX 7.0a installation, your video card and sound card drivers will be updated if necessary. The DirectX 7.0a files included with *Madden NFL 2000* include drivers for most video cards and sound cards from the major manufacturers of these peripherals. For new hardware, and for lesser-known brands of peripherals, you may have to contact your manufacturer to obtain drivers that support DirectX 7.0a.

After installing DirectX 7.0a, check to see if your video card or sound card drivers have DirectX 7.0a support:

1. Click the **Start** button on your Windows Taskbar, then click **Run...**
 2. In the Run dialog box, type **dxdiag**, then click **OK**.
 3. Look at the Display and Sound tabs.
- The Drivers section displays the driver version number and whether or not your driver is Certified by Microsoft as supporting DirectX 7.0a.
- ☐ If the Certified field states "No" in this section, you must contact your manufacturer to obtain updated drivers that support DirectX 7.0a.
 - ☐ If the Certified field states "Yes" in this section, your video card or sound card supports DirectX 7.0a and should work properly in DirectX 7.0a applications.

IMPORTANT NOTE: During DirectX installation, if you use a video card or sound card driver from your manufacturer that supports DirectX but is not yet Certified by Microsoft, you are prompted to replace the driver with a Certified driver. For video cards, we recommend not replacing your manufacturer's video card driver in this situation. Some manufacturers rely on their specific driver for functionality of their display utilities programs. Replacing the manufacturer's driver with Microsoft's driver may disable the functionality of these utility programs.

INSTALLING THE GAME

1. Start the Windows 95/98 operating system.
2. Insert the *Madden NFL 2000* CD into your CD drive. The Autorun screen appears.

NOTE: If the Autorun screen does not automatically appear, click the **Start** button on your Windows 95/98 taskbar, then click **Run...** At the Run dialog box, type **d:\autorun.exe**, then click **OK**. The Autorun screen appears. (Substitute the correct letter of your CD drive if other than 'D:')

3. To begin installing, click **PROCEED** then click **Next**. The Setup Type screen appears. Select an install size and click **Next**.

⇒ Select **Typical** (recommended for most users), Compact (fewer files are copied to your hard drive, but the game won't run as fast), or Custom (you choose which components are installed) installation.

4. Choose the destination folder in which you want *Madden NFL 2000* to be installed, then click **Next**.
 - ⇒ The default install directory is **C:\Program Files\EASPORTSMadden 2000**. To choose a different destination directory, click **Browse...**, select the desired directory, then click **Next**. The Choose Folder screen appears.
5. If you chose **Custom**, place a check mark next to all components you wish to install, then click **Next**.
6. Choose the **Start** menu folder you wish to install, the *Madden NFL 2000* shortcuts to, then click **Next**.
7. *Madden NFL 2000* is copied to your hard drive.
8. When the *Madden NFL 2000* file transfer is complete, you have the option to create a *Madden NFL 2000* shortcut on your desktop. Click **Yes** to accept, or **No** to decline. The *EA SPORTS* registration prompt appears.
9. Select **Register Now** to receive full customer support and to have a chance to win Electronic Arts™ merchandise, or select **Register Later**. The DirectX prompt appears.
10. Click your DirectX choice. (If you select **Yes**, follow the on-screen instructions for installing DirectX 7.0a and restart your computer.)
 - ☐ If you do not have DirectX 7.0a installed to your computer, or you have a version previous to 7.0a installed, we recommend you click **Yes**.
 - ☐ If you have DirectX 7.0a or higher installed to your computer, we recommend you click **No**.
11. When the Setup Complete prompt appears, click **OK**.
12. We recommend you also install the *Madden NFL 2000* patch which is included on the CD. Explore the CD and open the PATCH folder. Double-click the MADNPATCH file to install the patch.

NOTE: If you chose to add an icon to your desktop, but do not see the icon when the installation is complete, it may be hidden beneath another icon. Right click on the desktop, select **Arrange Icons**, then select **Auto Arrange**.

UNINSTALLING/REINSTALLING THE GAME

If you are having problems or the game did not install correctly the first time, we recommend re-installing the game.

1. Start the Windows 95/98 operating system.
2. Insert the *Madden NFL 2000* CD in your CD drive. The Launch screen appears.

NOTE: If the Launch screen does not automatically appear, click the **Start** button on your Windows 95/98 taskbar, then click **Run...** At the Run dialog box, type **d:\autorun**, then click **OK**. The Launch screen appears. (Substitute the correct letter of your CD drive if other than 'D:'.)

3. Click **REINSTALL**. After confirming that you want to re-install the game, follow the steps listed in *Installing the Game* on p. 4.

⇒ To uninstall the game, click **UNINSTALL** and confirm that you want to uninstall the game.

STARTING THE GAME

1. Start the Windows 95/98 operating system.
2. Start the *Madden NFL 2000* launcher.
3. Choose your desired graphics API (D3D, Glide, Non-Accelerated).
☐ If you selected D3D, choose your desired graphics board (2D/3D Card, 3D Accelerator).
4. Click "Play" to begin *Madden NFL 2000*.

NOTE: Please see the enclosed manual for gameplay instructions.

PROBLEMS WITH YOUR SOFTWARE?

If you are having a problem installing or using your software, we want to help.

- ☐ Please make sure you have thoroughly read the System Requirements and Installing the Game sections.

If you followed the directions and still have trouble installing or operating the software, on the next page are some hints that might help solve the problem.

CD PROBLEMS

A 8x-speed or faster CD-ROM drive is required to run *Madden NFL 2000*.

RECEIVE "FILE NOT FOUND" ERROR MESSAGE WHEN INSTALLING OR RUNNING THE GAME

- ☐ Make sure the CD is in the CD drive. The CD must be in the drive to install or run the game.
- ☐ Make sure the CD is not scratched or damaged.

CD-ROM PERFORMANCE PROBLEMS

- ☐ Make sure you are using a 32-bit native Windows 95/98 driver to control your CD-ROM drive. You can configure these drivers with the Device Manager found in **Start > Control Panel > System Properties**.
- ☐ Do not use a DOS-based 16-bit driver to control your CD-ROM (loaded in CONFIG.SYS) as it may significantly reduce performance.

CHOPPY OR STUTTERING VIDEO OR AUDIO

You may be able to resolve these problems by adjusting the CD-ROM read-ahead cache.

TO ADJUST THE READ-AHEAD CACHE:

1. At the Windows 95/98 desktop, right-click the My Computer icon, then choose **Properties** from the pop-up menu.
2. Click the Performance tab, then click **File System...**
3. Click the CD-ROM tab, then click in the **Optimize access pattern for:** box, and choose **QUAD-SPEED OR HIGHER**.
4. Move the **Supplemental cache size:** slider to **SMALL**, then click **Apply**.

NOTE: Moving the slider to **LARGE** does not improve *Madden NFL 2000* video performance, and may actually hinder performance by reserving RAM that would otherwise be available for the game.

MADDEN NFL 2000

EA SPORTS

EA SPORTS

MADDEN NFL 2000

VIDEO PROBLEMS

Madden NFL 2000 requires a PCI SVGA video card capable of 640x480 resolution with 65,535 colors (2 MB or more video memory).

NOTE: If your Windows 95/98 display driver does not support DirectDraw, you may experience difficulties installing or running *Madden NFL 2000*.

GENERAL VIDEO CARD INFORMATION

- During DirectX 6.0 installation, the DirectX 6.0 setup program attempts to install a display driver for your video card that supports DirectDraw. If your video card driver does not have DirectDraw support, the DirectX 6.0 setup program replaces your existing video card driver. In some cases, this may disable manufacturer specific utilities for your video card. If you want to keep these utilities functional, you may have to obtain the latest drivers with DirectDraw support directly from the manufacturer of your video card.
- If your video card driver already has DirectDraw support, but is not yet Certified by Microsoft, you are prompted to replace your current driver. In most cases, you should not replace your existing driver as it may disable manufacturer specific utilities for your video card. If you have video-related problems using the uncertified DirectDraw drivers from your manufacturer, you may solve these problems by reinstalling DirectX 6.0 and replacing your current video driver with a DirectX 6.0 video driver.

NOTE: Please refer to *DirectX 6.0 Installation Notes* on p. 3 for more information.

3-D ACCELERATOR TIPS

If you experience problems with the detection of your supported 3-D accelerator card, please refer to the documentation provided with your 3-D accelerator card.

VOODOO GRAPHICS BOARDS

Madden NFL 2000 requires the Glide run-time drivers for the Voodoo Graphics chipset. If you do not have the Glide run-time drivers for the Voodoo Graphics chipset installed or you have drivers previous to version 2.56, visit www.3dfx.com for the latest Glide drivers.

You may also contact your board manufacturer to obtain the latest drivers for your board.

NOTE: The minimum Glide driver versions for Voodoo Graphics Boards are: **Voodoo 1 = 2.48;**
Voodoo 2 = 2.56; Voodoo 3 = 2.60.

VOODOO RUSH BOARDS

Madden NFL 2000 requires the Glide 2.48 or higher run-time drivers specific to the Voodoo Rush chipset. If you do not have the Glide run-time drivers for the Voodoo Rush chipset installed or you have drivers previous to version 2.48, visit www.3dfx.com for the latest Glide drivers.

You may also contact your board manufacturer to obtain the latest drivers for your board.

MEMORY PROBLEMS

Madden NFL 2000 requires 32 MB RAM and Virtual Memory ENABLED. We advise letting Windows 95/98 manage the amount of virtual memory automatically (the default setting) and having at least 50 MB free hard drive space after installation.

SOUND PROBLEMS

Madden NFL 2000 requires a sound card with DirectSound support. If your sound card driver does not have DirectSound support, you may experience choppy or stuttering sound, or sound that cuts in and out. In this case, we recommend obtaining updated drivers from your sound card manufacturer.

INSTALLED SOUND CARD, BUT THERE IS NO SOUND

- Make sure your speakers or headphones are plugged into the appropriate jack and the volume control is turned up.

GENERAL SOUND CARD INFORMATION

- During DirectX 6.0 installation, the DirectX 6.0 setup program attempts to install a sound driver which has DirectSound support for your sound card. If your sound card driver does not support DirectSound, the DirectX 6.0 setup program attempts to replace your existing sound card driver.
- Please consult your sound card manufacturer for updated drivers if DirectX 6.0 DirectSound drivers are not available for your sound card.

NOTE: Please refer to *DirectX 6.0 Installation Notes* on p. 3 for more information.

CONTROLLER ISSUES

GRAVIS GAMEPAD™ AND 4 BUTTON CONTROLLERS

Although *Madden NFL 2000* supports multiple buttons when using a single controller, you are limited to 2-button support when using two gamepads (or other 4-button controllers) with a Y-cable adapter.

JOYSTICK CALIBRATION IN WINDOWS 95/98

In order for *Madden NFL 2000* to recognize your joystick, you must calibrate it from the Control Panel. To install or calibrate your joystick in Windows 95/98, access the Control Panel and launch the Game Controllers applet.

NOTE: Some gaming devices use their own applets or software for installation and calibration.

GRAVIS GRIP™ USERS

- ☐ Make sure the Gravis MultiPort is connected to the joystick port correctly.
- ☐ Make sure the Gravis MultiPort switch is in the left position for Grip support.
- ☐ Make sure that the Gravis Grip drivers are installed. If they are not, please refer to your Grip documentation for installation instructions.
- ☐ Make sure that the Gravis Grip controls are calibrated under Windows 95/98.

TO CALIBRATE THE GRAVIS GRIP IN WINDOWS 95/98:

- ☐ To install or calibrate your joystick in Windows 95/98, access the Control Panel and launch the Game Controllers applet.
- ☐ Once the steps are complete, the green light should activate on the left wing of the Gravis MultiPort.

NOTE: In Windows 95/98, the Gravis Grip requires that the Gameport Input/Output range be set to 0201-0201. Otherwise, the Grip may stop functioning after the current use upon rebooting, and you may need to reinstall the gameport and Grip drivers.

TO SET YOUR JOYSTICK INPUT/OUTPUT RANGE:

1. From the **Control Panel**, choose the **System** icon.
2. Select the **Device Manager** tab, then double-click the **Sound, video and game controllers** option.
3. Double-click the **Gameport Joystick** option, then select the **Resources** tab.
4. Make sure the **Use Automatic settings** box is unchecked, then select the **Change Setting** button.
5. Change the **Input/Output** range to 0201-0201.

Some Plug and Play sound cards do not allow this setting to be modified. Please contact your sound card manufacturer or Gravis for a resolution.

MODEM PROBLEMS

Madden NFL 2000 requires a 100% Hayes compatible 28.8 Kbps or faster modem for modem play. A high-speed (16550 UART) serial port is required for external modems.

GENERAL MODEM INFORMATION

Madden NFL 2000 uses the Windows 95/98 settings to initialize your modem. In order for your modem to work properly in the game, you must install it in Windows 95/98.

TO INSTALL YOUR MODEM IN WINDOWS 95/98:

1. Click the **Start** button from the Taskbar. The Start menu opens.
2. From the Start menu, highlight **Settings**, then select **Control Panel** from the pop-up menu.
3. From the Control Panel, click **Modems**.
4. If you have not installed a modem before, click **Next>** to let Windows 95/98 detect your modem.

If your modem came with a Windows 95/98 driver disk or .INF file, follow the manufacturers installation directions.

MODEM DOES NOT INITIALIZE

- ☐ Make sure your modem is installed correctly in Windows 95/98 and is turned ON.
- ☐ Make sure your modem works properly in Windows 95/98. If your modem is installed correctly and works with other Windows 95/98 modem applications, but you are having problems initializing it in *Madden NFL 2000*, try changing your modem type in Windows 95/98 to "Standard Modem."
- ☐ Some computers may have telephone answering or FAX applications pre-installed. These applications may tie up the modem, not allowing it access to other applications. Exit all applications that use your modem before playing a modem game.

NOTE: You may not be able to run your modem on COM4 if you have a video card based on the S3 chip set. If you experience difficulty making a modem connection on COM4, we suggest changing your modem or serial port to an alternate COM port.

NETWORK PROBLEMS

Madden NFL 2000 requires an IPX protocol network and network interface card for network play.

- ☐ If you experience difficulties with network play, consult your network manual or network administrator for specific information on loading drivers.

CONNECTION PROBLEMS

- ☐ Make sure the computers you are trying to connect are on the same network and are using the same protocol.

NETWORK PERFORMANCE ISSUES

There are various adjustments you can make to be sure you get the best performance out of your network game. These apply to the host computer as well as the clients. Try them on the host first as this may solve all the problems.

- ☐ Make sure the host computer (the one that creates the network game) is the fastest of the computers, as it controls the game speed.

- High-traffic networks slow the game down considerably. You may want to avoid playing the game at peak traffic hours, while there are large file transfers, or while there are print jobs being done.
- The slowest computer limits performance. Adjusting the resolution on a slow machine can help boost performance in a network game.

GENERAL NETWORK INFORMATION

- Do not run any Windows 95/98 applications that communicate over the network in the background (e.g., mail programs, personal schedulers, or network monitors).
- Make sure you have disabled Network Messages. If you are connected to a Novell network, contact your system administrator to disable network messages.

USING THE ELECTRONIC DOCUMENTATION

The electronic documentation uses Adobe Acrobat® 4.0. Installation files are included on the game CD.

1. Insert the game CD into the CD drive. If the autorun screen does not automatically appear, click **Start>Run...** Type `D:\autorun.exe` in the Open box and then click OK (substitute the correct letter if your CD-ROM drive is other than D:).
2. Click on Manual.

3. Select Install to launch the setup program. Follow the onscreen prompts.

- ✓ **Note:** If you already have Adobe Acrobat Reader 4.0 or higher installed, you may skip this step.
- 4. To view the docs, click View.
(If you get an error, you haven't installed Adobe Acrobat, or it installed incorrectly. Try uninstalling and re-installing it.)

UNINSTALLING

If you ever want to remove the Adobe Acrobat view from your system, use the Add/Remove Programs option under **Start>Settings>Control Panel**. Select Acrobat Reader and left-click Add/Remove Programs.

ACROBAT HELP

To activate help, select Help from the Acrobat menu bar. Then select Online Reader Guide. Once you install Adobe Acrobat, the Acrobat software license agreement appears on your hard drive in the default Acrobat installation directory.

TECHNICAL SUPPORT

The *Madden NFL 2000* CD includes a Windows Help file that provides solutions and answers to the most common difficulties and questions about how to properly use this product.

- ⇒ To access the Help file, click the Help button on the Autorun launcher, or select the EA SPORTS Help file from the **Start > Programs** menu.

The Help file contains a utility that allows you to contact EA via fax or e-mail. The utility automatically detects your system's hardware and organizes this information into a report.

- ⇒ To run the support utility from within the Help file, click the Contact Tech Support button.

TROUBLESHOOTING DOCUMENTS ONLINE!

Electronic Arts Product Support now offers troubleshooting guides that help overcome some common difficulties. If you have access to the World Wide Web, you can find these guides at http://www.ea.com/tech_support/help_guides/troubles.htm

Here you will find troubleshooting information on **DirectX**, **Joysticks**, **Modems**, and **Networks**, as well as information on regular system maintenance and performance. (For game-specific information and additional troubleshooting, visit our main page at http://www.ea.com/tech_support)

Abbreviated versions of these guides are included in the Help file on the CD for your convenience. If you have questions about the program, our Technical Support Department can help. Our web site contains up-to-date information on the most common difficulties with our products. This is the same information our product support technicians use to troubleshoot your performance issues. We update the product support pages daily, so please check here first for no-wait solutions:
http://www.ea.com/tech_support

If you are unable to find the information you need on our web site, please feel free to contact Technical Support via e-mail, phone, fax, or letter. *All messages are responded to in kind*—if you send in a request by fax, response will also come by fax. Please be sure to include the support utility's report in your e-mail message, fax, or letter:

- ⇒ To run the support utility, click the Tech Support button on the Autorun launcher.

If you need to talk to someone immediately, call us at (650) 628-4325 Monday through Friday between 8:30-11:45 AM or 1:00-4:30 PM, Pacific Standard Time. *Please have the utility's report printed and ready when you call.* This will help us answer your question in the shortest possible time. **No hints or codes are available from (650) 628-4325. You must call EA's HINTS & INFORMATION HOTLINE for hints, tips, or codes.**

EA Tech Support Fax: (650) 628-5999.

Electronic Arts Technical Support
P.O. Box 9025

Redwood City, CA 94063-9025

HOW TO REACH US ONLINE

INTERNET E-MAIL: support@ea.com
WARRANTY INQUIRIES: cs_warranty@ea.com
WORLD WIDE WEB: Access our Web Site at <http://www.ea.com>
FTP: Access our FTP Site at <ftp://ftp.ea.com>

If you live outside of the United States, you can contact one of our other offices.

In **Australia**, contact:

Electronic Arts Pty. Ltd.

P.O. Box 432

Southport Qld 4215, Australia

In the **United Kingdom**, contact:

Electronic Arts Ltd.

P.O. Box 835

Slough SL3 8XU, UK

Phone (753) 546465.

In **Australia**: For Technical Support and Game Hints and Tips, phone the EA HOTLINE:

1 902 261 600 (95 cents per min.) CTS 7 days a week 10:00 AM-8:00 PM.

If you are under 18 years of age parental consent required.

Need A Hint? Call EA's HINTS & INFORMATION HOTLINE for recorded hints, tips, and passwords
24 hours a day, 7 days a week!

In the **US**, dial 900-288-HINT (4468). 95c per minute.

In **CANADA**, dial 900-451-4873. \$1.15 (Canadian) per minute.

If you are under 18, be sure to get a parent's permission before calling. Hotline requires a touch-tone telephone. Call length determined by user; average length is four minutes. Messages subject to change without notice.

NOTICE

Electronic Arts reserves the right to make improvements in the product described in this manual at any time and without notice. This manual and the software described in this manual are copyrighted. All rights are reserved. No part of this manual or the described software may be copied, reproduced, translated, or reduced to any electronic medium or machine-readable form without the prior written consent of Electronic Arts, P.O. Box 9025, Redwood City, California 94062-9025. Attn: Customer Support Software and Documentation © 1999 Electronic Arts Inc. All rights reserved.

Pentium is a registered trademark of Intel Corporation. GamePad Pro, the Gravis logo, and Grip are trademarks of Advanced Gravis Computer Technology Ltd. Microsoft, Windows, SideWinder, DirectX 6.0, DirectDraw, Direct 3D, 3D Now! and DirectSound are trademarks or registered trademarks of Microsoft Corporation in the U.S. and/or other countries. Dolby is a trademark of Dolby Laboratories. 3Dfx Voodoo and Voodoo Rush are trademarks of 3Dfx Interactive, Inc. Environment Audio is a trademark of Creative Technologies Ltd. All rights reserved. All other trademarks are property of their respective owners.

EA SPORTS is an Electronic Arts™ brand.

John Madden Football, One-Button Mode, Coach & Click, Electronic Arts, the Electronic Arts logo, EA SPORTS, the EA SPORTS logo, and "It's in the game, it's in the game" are trademarks or registered trademarks of Electronic Arts Inc. in the U.S. and/or other countries. All rights reserved.

Officially licensed product of PLAYERS INC. The PLAYERS INC logo is a registered trademark of the NFL players. www.nflplayers.com © 1999 NFLP. Team names and logos are trademarks of the teams indicated. All other (NFL-related marks) are trademarks of the National Football League.

HOW TO REACH US ONLINE

INTERNET E-MAIL: support@ea.com
WARRANTY INQUIRIES: cs_warranty@ea.com
WORLD WIDE WEB: Access our Web Site at <http://www.ea.com>
FTP: Access our FTP Site at <ftp://ftp.ea.com>

If you live outside of the United States, you can contact one of our other offices.

In **Australia**, contact:

Electronic Arts Pty. Ltd.

P.O. Box 432

Southport Qld 4215, Australia

In the **United Kingdom**, contact:

Electronic Arts Ltd.

P.O. Box 835

Slough SL3 8XU, UK

Phone (753) 546465.

In **Australia**: For Technical Support and Game Hints and Tips, phone the EA HOTLINE:

1 902 261 600 (95 cents per min.) CTS 7 days a week 10:00 AM-8:00 PM.

If you are under 18 years of age parental consent required.

Need A Hint? Call EA's HINTS & INFORMATION HOTLINE for recorded hints, tips, and passwords
24 hours a day, 7 days a week!

In the **US**, dial 900-288-HINT (4468). 95c per minute.

In **CANADA**, dial 900-451-4873. \$1.15 (Canadian) per minute.

If you are under 18, be sure to get a parent's permission before calling. Hotline requires a touch-tone telephone. Call length determined by user; average length is four minutes. Messages subject to change without notice.

MADDEN NFL 2000

EA SPORTS

15 MADDEN NFL 2000

.....
To order the printed manual, please send this form along with check or money order for \$5.00 (U.S.\$ must be drawn on a U.S. or Canadian bank). Offer good while supplies last.

Electronic Arts
P.O. Box 9025
Redwood City, CA 94063-9025
Attn: CD Classic Manuals

Name _____
Address _____
City _____ State _____ Zip _____

Madden NFL 2000

If you need to contact us regarding the documentation, please call us at (650) 628-1900.

.....

Proof of Purchase
Madden NFL 2000

