

Instructions for Installing the 2016-01-12 Software Update

Note: This update requires bootloading new firmware onto the tiles.

Note: Step 6 is important.

Note: This update can be done via USB or via online if you have an internet connection from your SmartHub.

1. If doing USB-based update:
 - a) update will require a USB Thumb drive with at least 10MB of free space.
 - b) Go to <http://www.lellan.com/swdist/files.html> and download the zip file for the 2016-01-12 release onto the thumb drive in the top level directory.
 - c) Unzip the file - which should result in a directory named "lellan-updates_2016-01-12". Rename this directory to be just "lellan-updates".
 - d) Eject the thumb drive from your PC/Mac and insert into a running SmartHub.
2. **In the LellanApp, go to the System page. This will "preload" the System page so that the Reboot will work in Step 8 below.**
3. In the LellanApp, go to Settings->Software Updates. Run the "Check for Updates – USB" or "Check for Updates – Online", as appropriate, followed by "Install Updates – USB" or "Install Updates – Online" as appropriate.
4. After the updates finish, go to System and click the Reboot button.
5. After the SmartHub reboots, go back to Settings->Software Updates and click the Bootload button to start the process of loading new firmware onto the tiles.
6. Once the bootload procedure is done, you should be good to go.